

## Com Support

### **/comopen**

*Added in 1.9.4*

#### **/comopen name progid**

Opens a COM connection to object progid and assigns the connection a name.

*For 64 bit AdiIRC, MSScript com objects is not available unless you install <https://github.com/tablacus/TablacusScriptControl/releases>.*

#### **Parameters**

name - Connection name.

progid - ProgId to open. (e.g Excel.Application)

### **/comclose**

*Added in 1.9.4*

#### **/comclose name**

Closes the specified COM connection.

#### **Parameters**

name - Connection name.

### **/comlist**

*Added in 1.9.4*

#### **/comlist**

Lists all open COM connection.

### **/comreg**

*Added in 1.9.4*

#### **/comreg -u filename**

Registers/unregisters a COM DLL with windows.

#### **Switches**

-u - Unregister instead of register.

#### **Parameters**

filename - DLL filename to unregister/register.

## **\$com**

Added in 1.9.4

### **\$com(name|N)**

Returns name if connection is open, or name of Nth connection. N = 0 returns number of open connections.

#### **Parameters**

name|N - The connection name or the Nth connection.

#### **Properties**

.progid - The object name.  
.result - The value returned by the COM object member after the call  
.error - The error code if any.  
.errortext - The error text if any.  
.argerr - **TODO**  
.dispatch - [\\$true](#) if this is a dispatch pointer.  
.unknown - [\\$true](#) if this is a unknown pointer.

---

### **\$com(name, &bvar)**

Returns connection information for the connection and puts it into &bvar.

#### **Parameters**

name| - The connection name.  
&bvar - The &bvar to write to.

#### **Properties**

.progid - The object name.  
.result - The value returned by the COM object member after the call  
.error - The error code if any.  
.errortext - The error text if any.  
.argerr - **TODO**  
.dispatch - [\\$true](#) if this is a dispatch pointer.  
.unknown - [\\$true](#) if this is a unknown pointer.

---

### **\$com(name/N,varname)**

Returns value of the specified variable name.

#### **Parameters**

name/N - The connection name or the Nth connection.  
varname - Name of the referenced variable.

---

### **\$com(name,member,method,type1,value1,...,typeN,valueN)**

This calls a member of an open COM connection with the specified method and parameters.

Returns: 1 = ok, 0 = fail.

#### **Parameters**

name - Connection name.  
member - Member name.  
method - Combination of the following values added together:

```
1 = DISPATCH_METHOD
2 = DISPATCH_PROPERTYGET
4 = DISPATCH_PROPERTYPUT
```

```
8 = DISPATCH_PROPERTYPUTREF
```

type - The variable type, can be: i1, i2, i4, ui1, ui2, ui4, int, uint, r4, r8, cy, date, decimal, bool, bstr, variant, dispatch, unknown, error.

```
VB equivalents are: boolean, byte, currency, date, double, integer, long, single, string, variant.
```

```
To make a variable by reference, use * in the type name, eg. i1*
```

```
To assign a name to a variable for later reference after a call, append it to the type, eg. i1* varname
```

```
When using a variant you must also specify the variable type after it, eg. variant bool.
```

value - The value assigned to the variable type.

## \$comcall

*Added in 1.9.4*

**\$comcall(name,alias,member,method,type1,value1,...,typeN,valueN)**

This calls a member of an open COM connection with the specified method and parameters.

Uses the same format as [\\$com\(\)](#) apart from the alias. It is multi-threaded so it will not halt the script and will call the specified alias once the call returns.

Returns: 1 = ok, 0 = fail.

### Parameters

name - Connection name.

alias - Alias to call when the call is finished.

member - Member name.

method - Combination of the following values added together:

```
1 = DISPATCH_METHOD
2 = DISPATCH_PROPERTYGET
4 = DISPATCH_PROPERTYPUT
8 = DISPATCH_PROPERTYPUTREF
```

type - The variable type, can be: i1, i2, i4, ui1, ui2, ui4, int, uint, r4, r8, cy, date, decimal, bool, bstr, variant, dispatch, unknown, error.

```
VB equivalents are: boolean, byte, currency, date, double, integer, long, single, string, variant.
```

```
To make a variable by reference, use * in the type name, eg. i1*
```

```
To assign a name to a variable for later reference after a call, append it to the type, eg. i1* varname
```

```
When using a variant you must also specify the variable type after it, eg. variant bool.
```

value - The value assigned to the variable type.

## \$comerr

*Added in 1.9.4*

**\$comerr**

This should be checked after a call to any COM command or identifier. Returns 1 if there was an error, else 0.

## \$comval

*Added in 1.9.4*

### **\$comval(name,N,member, [&binvar])**

Returns COM member value for the Nth instance of the enumerated collection in name.

#### **Parameters**

name - Name of the COM connection.

N - If N = 0, return number of items, otherwise The Nth item.

member - Member value to get.

[&binvar] - Adds the result to the specified &binvar instead. (changes return value to number of bytes added)

#### **Properties**

.result - Used with [&binvar].