

AdIRC - Server - # 46

Added in 1.5

`/server [-switches] [host/ip address/network label] [port] [password] [-additional switches..]`

Connects to a new server.

Switches

Switch	Description
-4	Connect to ipv4 addresses.
-6	Connect to ipv6 addresses.
-e	Indicates connection should be a SSL/TLS connection.
-m	Indicates connection should happen in a new server window.
-n	Indicates connection should happen in a new server window, but not connect.
-p	Prevents the perform/commands from being applied.
-f	Prevents the channellist from popping up.
-o	Prevents the autojoining of channels from being applied.
-c	Prevents the on CONNECT event from being triggered.
-z	Minimizes the new server window.
-t	Indicates connection should be a STARTTLS connection.
-s	TODO
-a	TODO
-r	TODO
-w	TODO
-u	TODO
-l method password	Use login method to identify nick

Parameters

Parameter	Description
[host/network label]	Host to join, can be a ip address or host name, can also be a network label from the Serverlist or the default Serverlist .
[port]	Port to use. (+port indicates connection should be a SSL/TLS connection, *port indicates a STARTTLS connection)
[password]	The server password to use, normally used for bnc login.

Additional switches

Switch	Description
[-j/-jn/-join #channel pass]	Channels to join as a comma separated list. (if -jn or -j -n is used, the channels are minimized)
[-new/-m]	Indicates connection should happen in a new server window.
[-forcessl N]	Forces a specific SSL/TLS version, 0 = ssl2, 1 = ssl3, 2 = tls1.0, 3 = tls1.1, 4 = tls1.2 (tls1.1 and tls1.2 is only available in the .net 4+ version)
[-n]	Indicates connection should happen in a new server window, but not connect.

[-z]	Minimizes the new server window.
[-p/-pass password]	Another way to set the server password to use, normally used for bnc login.
[-e/-ssl]	Indicates connection should be a SSL/TLS connection.
[-t]	Indicates connection should be a STARTTLS connection.
[-u/-user username]	The server login username to use, normally used for bnc login.
[-nick nick]	The nick to use.
[-an/-anick alternate nick]	Alternative nick to use.
[-r/-real fullname]	Fullname to use.
[-port port]	Another way to set what port to use.
[-i nick anick email name]	Another way to set nick, alternative nick, server username and fullname.
[-d encoding]	Encoding to use on this server.
[-cert file]	Custom SSL client certificate to use for this server.
[-key file]	Custom SSL client certificate to use for this server.
[-4]	Connect to ipv4 addresses.
[-6]	Connect to ipv6 addresses.
[-g]	Prioritize ipv6 addresses.
[-x 4 5 h n hostname port username password]	Connect using custom Sockv4/Sockv5/http or no proxy.

Example

```
; Connect irc.nordicirc.com port 6667 in a new server window with nick MyNick, alt nick MyNick_ and join channels #chan1,#chan2,#chan3.
```

```
/server -m irc.nordicirc.com 6667 -nick MyNick -an MyNick_ -j #chan1,#chan2,#chan3
```

```
; Connect a network label from the Serverlist named 'NordicIRC'
```

```
/server -m NordicIRC
```

```
; Connect a network label from the default Serverlist named 'Freenode'
```

```
/server -m Freenode
```